
SSSSSSSSSSS YYY YYY SSSSSSSSSSS
SSSSSSSSSSS YYY YYY SSSSSSSSSSS
SSSSSSSSSSS YYY YYY SSSSSSSSSSS
SSS YYY YYY SSS
SSS YYY YYY SSS
SSS YYY YYY SSS
SSS YYY YYY SSS
SSS YYY YYY SSS
SSS YYY YYY SSS
SSSSSSSSS YYY SSSSSSSSS
SSSSSSSSS YYY SSSSSSSSS
SSSSSSSSS YYY SSSSSSSSS
SSS YYY SSS
SSS YYY SSS
SSS YYY SSS
SSS YYY SSS
SSS YYY SSS
SSS YYY SSS
SSSSSSSSSSS YYY SSSSSSSSSSS
SSSSSSSSSSS YYY SSSSSSSSSSS
SSSSSSSSSSS YYY SSSSSSSSSSS

FILEID**SYSFORCEX

```
  SSSSSSSS  YY      YY   SSSSSSSS  FFFFFFFFFF    000000    RRRRRRRR     CCCCCCCC  EEEEEEEEEE  XX      XX
  SSSSSSSS  YY      YY   SSSSSSSS  FFFFFFFFFF    000000    RRRRRRRR     CCCCCCCC  EEEEEEEEEE  XX      XX
SS          YY      YY SS          FF          00      00  RR      RR CC          EE          XX      XX
SS          YY      YY SS          FF          00      00  RR      RR CC          EE          XX      XX
SS            YY  YY   SS          FF          00      00  RR      RR CC          EE            XX  XX
SS            YY  YY   SS          FF          00      00  RR      RR CC          EE            XX  XX
  SSSSSS        YY       SSSSSS    FFFFFFFF    00      00  RRRRRRRR   CC          EEEEEEEE        XX
  SSSSSS        YY       SSSSSS    FFFFFFFF    00      00  RRRRRRRR   CC          EEEEEEEE        XX
        SS      YY             SS  FF          00      00  RR  RR     CC          EE            XX  XX
        SS      YY             SS  FF          00      00  RR  RR     CC          EE            XX  XX
        SS      YY             SS  FF          00      00  RR    RR   CC          EE          XX      XX      ....
        SS      YY             SS  FF          00      00  RR    RR   CC          EE          XX      XX      ....
SSSSSSSS        YY     SSSSSSSS    FF            000000    RR      RR   CCCCCCCC  EEEEEEEEEE  XX      XX      ....
SSSSSSSS        YY     SSSSSSSS    FF            000000    RR      RR   CCCCCCCC  EEEEEEEEEE  XX      XX      ....

LL              IIIIII     SSSSSSSS
LL              IIIIII     SSSSSSSS
LL                II     SS
LL                II     SS
LL                II     SS
LL                II     SS
LL                II       SSSSSS
LL                II       SSSSSS
LL                II             SS
LL                II             SS
LL                II             SS
LL                II             SS
LLLLLLLLLL      IIIIII   SSSSSSSS
LLLLLLLLLL      IIIIII   SSSSSSSS
```

Table of contents

(1) 39 HISTORY ; DETAILED
(1) 48 DECLARATIONS
(1) 72 EXE$FORCEX - FORCE EXIT SYSTEM SERVICE

```
0000     1
0000     2          .TITLE  SYSFORCEX FORCE EXIT SYSTEM SERVICE
0000     3          .IDENT  'V04-000'
0000     4
0000     5 ;
0000     6 ;*****************************************************************************
0000     7 ;*                                                                           *
0000     8 ;*  COPYRIGHT (c) 1978, 1980, 1982, 1984 BY                                  *
0000     9 ;*  DIGITAL EQUIPMENT CORPORATION, MAYNARD, MASSACHUSETTS.                   *
0000    10 ;*  ALL RIGHTS RESERVED.                                                     *
0000    11 ;*                                                                           *
0000    12 ;*  THIS SOFTWARE IS FURNISHED UNDER A LICENSE AND MAY BE USED AND COPIED    *
0000    13 ;*  ONLY IN  ACCORDANCE WITH  THE  TERMS  OF  SUCH  LICENSE  AND WITH THE   *
0000    14 ;*  INCLUSION OF THE ABOVE COPYRIGHT NOTICE. THIS SOFTWARE OR  ANY  OTHER    *
0000    15 ;*  COPIES THEREOF MAY NOT BE PROVIDED OR OTHERWISE MADE AVAILABLE TO ANY    *
0000    16 ;*  OTHER PERSON.  NO TITLE TO AND OWNERSHIP OF  THE  SOFTWARE IS  HEREBY    *
0000    17 ;*  TRANSFERRED.                                                             *
0000    18 ;*                                                                           *
0000    19 ;*  THE INFORMATION IN THIS SOFTWARE IS  SUBJECT TO CHANGE WITHOUT NOTICE    *
0000    20 ;*  AND  SHOULD  NOT  BE  CONSTRUED AS  A COMMITMENT BY DIGITAL EQUIPMENT   *
0000    21 ;*  CORPORATION.                                                             *
0000    22 ;*                                                                           *
0000    23 ;*  DIGITAL ASSUMES NO RESPONSIBILITY FOR THE USE  OR  RELIABILITY OF ITS    *
0000    24 ;*  SOFTWARE ON EQUIPMENT WHICH IS NOT SUPPLIED BY DIGITAL.                  *
0000    25 ;*                                                                           *
0000    26 ;*                                                                           *
0000    27 ;*****************************************************************************
0000    28
0000    29 ;++
0000    30 ; FACILITY: EXECUTIVE, SYSTEM SERVICES
0000    31 ;
0000    32 ; ABSTRACT:
0000    33 ;
0000    34 ; ENVIRONMENT:
0000    35 ;
0000    36 ;--
0000    37 ;
0000    38 ;          .PAGE
0000    39           .SBTTL  HISTORY                         ; DETAILED
0000    40 ;
0000    41 ; AUTHOR:          R. HUSTVEDT       CREATION DATE: 1-OCT-76
0000    42 ;
0000    43 ; MODIFIED BY:
0000    44 ;          , : VERSION
0000    45 ; 01       -
0000    46
```

```
                     0000     48          .SBTTL  DECLARATIONS
                     0000     49
                     0000     50 ;
                     0000     51 ; INCLUDE FILES:
                     0000     52 ;
                     0000     53
                     0000     54          $ACBDEF                         ; DEFINE AST CONTROL BLOCK
                     0000     55          $IPLDEF                         ; DEFINE INTERRUPT PRIORITY LEVELS
                     0000     56          $PCBDEF                         ; DEFINE PROCESS CONTROL BLOCK
                     0000     57          $PRDEF                          ; DEFINE PROCESSOR REGISTERS
                     0000     58          $PRIDEF                         ; DEFINE PRIORITY INCREMENT CLASSES
                     0000     59          $SSDEF                          ; DEFINE STATUS CODES
                     0000     60
                     0000     61 ;
                     0000     62 ; EQUATED SYMBOLS:
                     0000     63 ;
                     0000     64
00000000             0000     65 ASTEXIT=0                               ; CHMK CODE FOR ASTEXIT
0000000C             0000     66 CODE=12                                 ; DISPLACEMENT TO CODE PARAMETER
                     0000     67 ;
                     0000     68 ; OWN STORAGE:
                     0000     69 ;
                     0000     70
```

```
                                0000     72          .SBTTL  EXE$FORCEX - FORCE EXIT SYSTEM SERVICE
                                0000     73
                                0000     74 ;++
                                0000     75 ; FUNCTIONAL DESCRIPTION:
                                0000     76 ;
                                0000     77 ; CALLING SEQUENCE:
                                0000     78 ;       CALLG   ARGLIST,EXE$FORCEX
                                0000     79 ;
                                0000     80 ; INPUT PARAMETERS:
                                0000     81 ;       PIDADR(AP) - ADDRESS OF PID (WRITTEN)
                                0000     82 ;       PRCNAM(AP) - ADDRESS OF PROCESS LOGICAL NAME
                                0000     83 ;       CODE(AP) - COMPLETION CODE TO BE USED FOR EXIT CALL
                                0000     84 ;       R4 - PCB ADDRESS OF CURRENT PROCESS
                                0000     85 ;
                                0000     86 ; IMPLICIT INPUTS:
                                0000     87 ;       NONE
                                0000     88 ;
                                0000     89 ; OUTPUT PARAMETERS:
                                0000     90 ;       @PIDADR(AP) - PID OF PROCESS FOR WHICH EXIT WAS FORCED
                                0000     91 ;       R0 - COMPLETION STATUS
                                0000     92 ;
                                0000     93 ; IMPLICIT OUTPUTS:
                                0000     94 ;       NONE
                                0000     95 ;
                                0000     96 ; COMPLETION CODES:
                                0000     97 ;       SS$_NORMAL  -  SUCCESSFUL COMPLETION
                                0000     98 ;       SS$_INSFMEM -  INSUFFICIENT DYNAMIC MEMORY
                                0000     99 ;       SS$_NONEXPR -  NON-EXISTENT PROCESS
                                0000    100 ;       SS$_NOPRIV  -  INSUFFICIENT PRIVILEGE TO CONTROL DETACHED PROCESS
                                0000    101 ;
                                0000    102 ; SIDE EFFECTS:
                                0000    103 ;       NONE
                                0000    104 ;
                                0000    105 ;--
                                0000    106
                                0000    107 EXE$FORCEX::                                ; FORCE EXIT SYSTEM SERVICE
                       003C     0000    108          .WORD   ^M<R2,R3,R4,R5>            ; SAVE REGISTERS R2-R5
             FFFB'      30     0002    109          BSBW    EXE$NAMPID                 ; CONVERT NAME-PID PAIR
                                0005    110          SETIPL  #0                         ; DROP IPL
               2B 50    E9     0008    111          BLBC    R0,20$                     ; EXIT IF ERROR
23 24 A4       02    E2     000B    112          BBSS    #PCB$V_FORCPEN,PCB$L_STS(R4),10$; FORCE EXIT ALREADY PENDING
                  51    DD     0010    113          PUSHL   R1                         ; SAVE PID
             FFEB'      30     0012    114          BSBW    EXE$ALLOCIRP               ; ALLOCATE AST CONTROL BLOCK
               1E 50    E9     0015    115          BLBC    R0,20$                     ; EXIT IF ERROR
   0B A2       03    90     0018    116          MOVB    #3,ACB$B_RMOD(R2)          ; SET ACCESS MODE
   0C A2       8E    D0     001C    117          MOVL    (SP)+,ACB$L_PID(R2)        ; SET PID OF DESTINATION
10 A2       37'AF    9E     0020    118          MOVAB   B^DOEXIT,ACB$L_AST(R2)     ; AND ADDRESS OF AST ROUTINE
14 A2       0C AC    D0     0025    119          MOVL    CODE(AP),ACB$L_ASTPRM(R2); SET CODE FOR EXIT CALL
            55  52    D0     002A    120          MOVL    R2,R5                      ; AST CONTROL BLOCK ADDRESS FOR QAST
            52  02    9A     002D    121          MOVZBL  #PRI$_RESAVL,R2            ; SET PRIORITY INCREMENT CLASS
             FFCD'      30     0030    122          BSBW    SCH$QAST                   ; QUEUE ACB FOR TARGET PROCESS
            50  01    3C     0033    123 10$:     MOVZWL  #SS$_NORMAL,R0             ; SET NORMAL COMPLETION STATUS
                       04     0036    124 20$:     RET                                ; AND RETURN TO CALLER
                              0037    125
                              0037    126
```

```
                     0037   128 ;
                     0037   129 ; PERFORM EXIT AS A RESULT OF USER MODE AST IN THE CONTEXT OF THE
                     0037   130 ; TARGET PROCESS.
                     0037   131 ;
                     0037   132
                     0037   133 DOEXIT:                                              ;
           0000      0037   134          .WORD   0                                   ; NULL REGISTER SAVE MASK
        00   BC     0039   135          CHMK    #ASTEXIT                            ; CLEAR AST ACTIVE FLAG
                     003B   136          $EXIT_S 4(AP)                               ; MAKE EXIT CALL
                     0045   137
                     0045   138
                     0045   139          .END
```

```
ACB$B_RMOD                      = 0000000B
ACB$L_AST                       = 00000010
ACB$L_ASTPRM                    = 00000014
ACB$L_PID                       = 0000000C
ASTEXIT                         = 00000000
CODE                            = 0000000C
DOEXIT                            00000037 R      01
EXE$ALLOCIRP                      ******** X      01
EXE$FORCEX                        00000000 RG     01
EXE$NAMPID                        ******** X      01
PCB$L_STS                       = 00000024
PCB$V_FORCPEN                   = 00000002
PR$_IPL                         = 00000012
PRI$_RESAVL                     = 00000002
SCH$QAST                          ******** X      01
SS$_NORMAL                      = 00000001
SYS$EXIT                          ******** GX     01
```

Psect synopsis

PSECT name	Allocation	PSECT No.	Attributes
. ABS .	00000000 (0.)	00 (0.)	NOPIC USR CON ABS LCL NOSHR NOEXE NORD NOWRT NOVEC BYTE
. BLANK .	00000045 (69.)	01 (1.)	NOPIC USR CON REL LCL NOSHR EXE RD WRT NOVEC BYTE
ABS	00000000 (0.)	02 (2.)	NOPIC USR CON ABS LCL NOSHR EXE RD WRT NOVEC BYTE

Performance indicators

Phase	Page faults	CPU Time	Elapsed Time
Initialization	31	00:00:00.06	00:00:01.17
Command processing	109	00:00:00.58	00:00:06.28
Pass 1	242	00:00:06.02	00:00:18.03
Symbol table sort	0	00:00:01.05	00:00:04.28
Pass 2	40	00:00:01.03	00:00:04.65
Symbol table output	4	00:00:00.03	00:00:00.04
Psect synopsis output	1	00:00:00.02	00:00:00.02
Cross-reference output	0	00:00:00.00	00:00:00.00
Assembler run totals	429	00:00:08.81	00:00:34.49

```
The working set limit was 1200 pages.
33261 bytes (65 pages) of virtual memory were used to buffer the intermediate code.
There were 40 pages of symbol table space allocated to hold 667 non-local and 2 local symbols.
139 source lines were read in Pass 1, producing 12 object records in Pass 2.
15 pages of virtual memory were used to define 14 macros.
```

```
                          +----------------------------+
                          ! Macro library statistics !
                          +----------------------------+

Macro library name                          Macros defined
------------------                          --------------
_$255$DUA28:[SYS.OBJ]LIB.MLB;1                           5
_$255$DUA28:[SYSLIB]STARLET.MLB;2                        6
TOTALS (all libraries)                                  11

753 GETS were required to define 11 macros.

There were no errors, warnings or information messages.

MACRO/LIS=LIS$:SYSFORCEX/OBJ=OBJ$:SYSFORCEX MSRC$:SYSFORCEX/UPDATE=(ENH$:SYSFORCEX)+EXECML$/LIB
```

SYSGETJPI
LIS

SYSERAPAT
LIS

SYSFAO
LIS

SYSGETDVI
LIS

SYSEXIT
LIS

SYSEVTSRV
LIS

SYSFORCEX
LIS